

---

# **CORK and BPR documentation Documentation**

***Release 0.2***

**Martin Heesemann**

May 18, 2013



# CONTENTS

<b>1</b>	<b>Before youo go to sea</b>	<b>3</b>
1.1	Make sure you have a working computer . . . . .	3
<b>2</b>	<b>CORK and BPR Field Guide</b>	<b>5</b>
2.1	Crib sheets . . . . .	5
2.2	Howto's . . . . .	6
2.3	Glossary . . . . .	10
<b>3</b>	<b>CORK Computer Setup</b>	<b>13</b>
3.1	Required software . . . . .	13
<b>4</b>	<b>Manpages</b>	<b>15</b>
<b>5</b>	<b>Todos</b>	<b>19</b>
<b>6</b>	<b>Python modules</b>	<b>21</b>
<b>7</b>	<b>References</b>	<b>23</b>
	<b>Index</b>	<b>25</b>



The wiki <http://www.corkobservatories.org/pmwiki/index.php>

Unfortunately, the wiki site is not very well maintained in the moment.

I do maintain a version controlled software repository that contains all the programs that you need to deal with CORKs and the downloaded data: <http://corkobservatory.svn.sourceforge.net/viewvc/corkobservatory/>

This repository is used to keep the computers that are used to download data updated and in sync. It also contains all calibration and site information (see CalibrationFiles) and the details of the instrument configurations (see ParameterFiles). If you want to contribute to that information, you need to install subversion (svn) to stay up to date and push new updates to the software repository. Or you can ask me to make the modifications. I also use the repository to maintain some documentation of the software that you can access here: <http://corkobservatory.sourceforge.net/>



# BEFORE YOU GO TO SEA

## 1.1 Make sure you have a working computer

A computer running Linux is the simplest platform to install and run the CORK software on.

### 1.1.1 Verify that your software is still current

```
[mheesema@sciserv C-tools]$ svn log -r base:head
```





---

# CORK AND BPR FIELD GUIDE

---

## 2.1 Crib sheets

### 2.1.1 Simple health check and download

1. Make sure laptop clock is synchronized (see *Sync to NTP*)
2. Create a working directory (see *Setup working directory*)
3. Connect instrument to computer (see *Connecting the Instrument*)
4. Turn on communication and power **after** connection is established make sure power and comms are off before ODI connector is removed from parking position
5. Run mlterm, making sure to use a reasonable log-file name (see *Starting mlterm*)
6. **Get instrument stats F**
  - (a) Take note of clock drift (do **not** synchronize the clock, later on)
  - (b) Take note of predicted download times
7. **Get basic logger settings I**
  - (a) Take note of download baud-rate (115200 for NEPTUNE instruments)
  - (b) Take note of control baud-rate (115200 for NEPTUNE instruments)
8. Consider to increase download speed (see *Increase download speed*)
9. Download data D, making sure to use a reasonable file name
10. Get instrument stats F again
11. **Deploy instrument and quit Z** PI might suggest real-time monitoring while following next steps
12. Backup data (\*.raw) to USB key (see *Backup data*)
13. **Check data integrity**
  - (a) `run mlbin xxxx.raw` strips off file system and generate xxxx.bin (there should be no errors)
  - (b) `run dumpBin.py -a -n -t -s xxxx.bin > xxxx.dmp` Does some integrity checking and creates ASCII dump
  - (c) `run tail xxxxx.dmp to see statistics` Discuss with PI
14. Contact PI and discuss whether to clear memory
15. Backup \*.log files and sent \*.log and \*.raw files to PI

16. Make sure the communication and power lines are turned off **before** the under water mateable connector is disconnected.

## 2.2 Howto's

### 2.2.1 Linux

Working with the *HP-Mini* s that are used to download data from *CORK* s and *BPR* s requires some basic Linux skills. This section provides some recipes for common tasks.




Figure 2.1: Linux session with terminal window.

### Open a terminal window

Click on the terminal icon



to open a command-line terminal window. If needed you can create tabs with additional terminals from the **File** menu.

### Basic Linux Commands

**pwd** Prints the current working directory

**ls** Lists the files in the current directory. Use `ls -lh` to get more details about the files.

**mkdir** Creates a new subdirectory (e.g. `mkdir TestDirectory`)

**rm** Deletes specified files. `rm -r` also deletes directories. **Careful**, there is no way back!!!

**cd** Change into specified directory. As with all other commands, pressing `Tab` does an auto-complete—try it!

## Setup working directory


Before you start to communicate with a CORK or BPR, create a working directory under `/home/corks/Cruises` or `/home/corks/Tests`—what ever seems more appropriate. If you are on a cruise you might consider creating subdirectories for individual instruments. In a terminal window change the directory to the working directory and execute `cp /home/corks/corkobservatory/CalibrationFiles/\*.txt ./` to copy some calibration files into your working directory (see [mlterm calibration files](#)). Now, you're all set to begin communication with the logger, data download, and post-processing.

If all of this is not clear to you, you might want to read [Open a terminal window](#) and [Basic Linux Commands](#) first.

## Backup data

After downloading data from an instrument and before clearing the memory, make sure that you make at least one backup copy of the data is on a USB key. To make a backup follow these steps:


1. Insert USB key (it will be mounted under `/media`)
2. Find out the name/directory of the drive (`ls /media`)
3. Copy files `cp file1.raw [file2.log ...] /media/nameOfUSB` (`cp -R` let's you copy directories recursively)
4. Unmount USB key (click computer icon, hover over device—e.g. KINGSTON, click eject symbol)



5. Now the eject symbol should have disappeared and you can safely remove the device

## Sync to NTP

1. Boot up the [HP-Mini](#) and make sure that wireless networking is enabled (both LEDs on front are blue) if you do not have a cabled connection.
2. **Make sure you are connected to a network**
  - (a) Hover over icon on the bottom tool bar (globe, or wireless signal) and check if `eth0` (cable) or `eth1` (wireless) are connected)



- (b) If no connection is up, click on the globe and connect to a network (e.g. TGT if you happen to be on the Thompson)

3. Open a terminal window and monitor the NTP log file (`tail --follow /var/log/ntp - Ctrl-c to quit`)

- (a) Look for synchronized to xxx.xxx.xxx.xxx, stratum ? that happened within the last 30 min or so.
- (b) If you do not see anything, try to restart NTP (`sudo /sbin/service ntp restart` – you will need the root password)
- (c) If after a few minutes you still do not see any signs of synchronization, you might have to [Setup NTP](#)

## Setup NTP

---

### Todo

Add section about NTP setup

---

## 2.2.2 Instrument setup

### Connecting the Instrument

Most modern CORKs and BPR have an RS-422 serial interface. We found that [Moxa UPort](#) USB-to-RS422 converters provide the most reliable connections.

## 2.2.3 mlterm

### Starting mlterm

Before running mlterm in a command-line terminal, make sure you are in a directory that is appropriately setup (see [Setup working directory](#)). If you simply run mlterm, the session will be logged (appended) to a logfile named after the current date. It is advisable to use the `-l myLogfile.log` command-line option, to choose a descriptive name. On startup, mlterm tries all possible baudrates to connect to the instrument. If the baudrate is known (115200 for all NEPTUNE instruments) the `-b 115200` option provides a quicker initialization. As shown in [Linux session with terminal window](#), the instrument should wake up after a short period of time and after hitting `Enter` the high-level mlterm menu will be presented.

### Increase download speed

Start mlterm (see [Starting mlterm](#)) and from high-level menu proceed as follows:

1. Enter low-level mode by pressing `P` and `Enter`

2. Bring up MT01 menu `Ctrl-s`
3. Choose option to change download baudrate `3`
4. Choose appropriate download speed (most likely `8 230400`)
5. Quit MT01 menu `Q`
6. Quit low-level interface `Esc`

Now, you are all set to start the download procedure.

Note, the download baudrate will automatically be set to it's default if you deploy the instrument by quitting `mlterm` with `Z` or after a timeout period of 30 minutes.

## 2.2.4 Data post-processing

After downloading raw data from an instrument (see [Simple health check and download](#)) the data has to post-processed.

First, `mlbin` has to be applied (`mlbin filename.raw`) to turn the `*.raw` file into a `*.bin` file. The `*.raw` files still contain the filesystem of the flash card and recovery information in case there were errors in the data transmission. `mlbin` strips off the filesystem and tries to fix any errors that might have occurred. The `*.bin` file only contains data records in binary counts.

`mldat9` (`mldat9 filename.bin`) is the standart utility to calibrate `*.bin` data and write the results into a `*.dat` ASCII file. In order to use `mldat9` you have to `cd` into the directory with the `*.bin` file and make sure there is also a current set of calibration files in the directory (see [Setup working directory](#)). While running `mldat9` you will be ask whether the temperatures are measured using a platinum sensor or a thermistor. Platinum sensors are mostly used in CORKs and BPRs installed past 2009 and have two-digit serial numbers, while themistors have one digit serial numbers. The serial numbers are shown in the `sites.txt` calibratrion file (see [mlterm calibration files](#)) and should be noted in the respective `*.par` file under `~/corkobservatory/ParameterFiles`. Furthermore, you are asked whether the Paroscientific gauge measures pressure and temperature or pressure only. If you do not know the answer you can lookup the gauge serial numbers that are mentionend in `sites.txt` in `parosci.txt` and check whether `U0`, `Y1`, `Y2` are zero (pressure only) or non zeros (pressure and temperature). Then you have to select a data format (typically “4. Parosci temperature compensated pressure”) and a site description which is a line from the `site.txt` calibration file. The site description has the following format:

number:	description_rtcID	deploymentMonth	temperatureSerial	parosciSerial	parosciSerial	...
3:	1027C_89	Jul10	98	120238	120239	...

`mldat9` automatically removes spikes from the paros pressure and temperature channels that get sometimes generated by the measurement system and is convinient to use, but it has certain limitations:

1. `mldat9` has problems with partial records that can sometimes occur especially on systems that occasionally switch between battery and cabled mode.
2. `mldat9` cannot cope with instruments that have a mix between gauges that measure temperature and pressure and pressure only. These configurations exist especially for CORKs which have many gauges and are designed to operated in cabled mode.

To cope with these problems two Python programs were developed that can be used instead of `mldat9` (see [Install dependencies for Python scripts](#)). The first script `dumpBin.py` can be used fix `*.bin` files by eliminating partial records, remove spikes, find problems, and dump the binary counts into an ASCII format that is human readable and can be calibrated using a `calibrateLogfile.py`.

A common workflow to process `filename.bin` using these scripts would be:

1. Fix data problems using `dumpBin.py -n -s -a -t -b filename_fixed.bin filename.bin`  
`> filename.dmp`
  - `filename_fixed.bin` will contain all complete data records

- filename.dmp will contain ASCII representation of binary data and debugging information
2. Dump despiked data (only works with clean data) for calibration “`dumpBin.py -d filename_fixed.bin > filename_despiked.dmp`
  3. Calibrate the data `calibrateLogfile.py -c calibrationName filename_despiked.dmp > filename_despiked.dat`
    - `calibrateLogfile.py` also works with data from stdin, so the last two steps can be combined using a pipe: `dumpBin.py -d filename_fixed.bin | calibrateLogfile.py -c calibrationName > filename_despiked.dat`
    - Run `calibrateLogfile.py -l` to get a list of available calibrations. New calibrations can be defined in `calibrateData.py`.

Run `dumpBin.py --help` and `calibrateLogfile.py --help` to study all available the commandline options.

### mlterm calibration files

There are three different calibration files:

**parosci.txt** Calibration coefficients for Paroscientific pressure gauges

**platinum.txt** Calibration coefficients for platinum housing temperature sensors

**therms.txt** Calibration coefficient housing temperature thermistors

**sites.txt** Data base that associates deployment locations and times, logger IDs, and sensor IDs. This information is used for calibration routines.

**Note**, mldat and mlterm only support only up to 30 lines in sites.txt.

---

### Todo

Changed mldat (`wrt2dat.c - DEFINE MAXSITES`) to support sites.txt files with more than 30 lines. Add same functionality to mldat (`formatdata.c`) requires CORK simulator for testing...

---

## 2.3 Glossary

**AWQ bulkhead connector** CORK pressure cases usually have an 6 pie AWQ bulkhead connector, that connects to an 7-pin ODI or SEACON underwater mateable connector. BPR pressure cases usually have an 2 piece AWQ bulkhead connector, that connects to a 7-pin ODI connector.



ODI to two pie AWQ cable

**BPR** Bottom Pressure Recorder

**CORK** Circulation Obviation Retro-fit Kit

**HP-Mini** There are four HP-Minis setup to do CORK and BPR downloads around the world. It is also possible to compile the communication software for Mac and there is an image for VirtualBox that makes it possible to run the software on a Linux virtual machine under windows.



**Moxa UPort** The Moxa UPort USB-2-RS422 to adapter provides superior download speeds over other brands. Unfortunately, the driver only supports older versions of Linux. UPDATE: There is a new driver released in summer 2012. Also, Nic Scott mentioned wrapping Windows drivers under Linux







# CORK COMPUTER SETUP

## 3.1 Required software

A computer running Linux is the simplest platform to install and run the CORK software on. It is also known to run on Mac computers and most data data processing can be done on Windows machines, but mlterm the program used to communicate with CORKs and download the data does not work under windows and the necessary development environment to compile various C-programs might be challenging to setup on Mac.

### 3.1.1 Check out the CORK software repository

CORK software, calibration and parameter files are maintained at the [CORK Observatory Software Repository](https://corkobservatory.svn.sourceforge.net/svnroot/corkobservatory).

It is best to have svn installed to check out the code. Check if svn is installed by running `svn --help`. If there is not help displayed you have to install svn e.g. by running `sodu yum install subversion`.

Now, go into the home directory of the cork user (`cd ~`) and run

```
svn co https://svn.code.sf.net/p/corkobservatory/code/ corkobservatory
```

---

**Note:** SourceForge changed their naming scheme. Do *not* use the following anymore: `svn co https://corkobservatory.svn.sourceforge.net/svnroot/corkobservatory corkobservatory`

If you are stuck at revision 65 after update Updated to revision 65.

```
svn info URL: https://corkobservatory.svn.sourceforge.net/svnroot/corkobservatory
```

```
svn switch --relocate https://corkobservatory.svn.sourceforge.net/svnroot/corkobservatory  
https://svn.code.sf.net/p/corkobservatory/code/
```

After update revision should be greater than Revision: 73

---

This will create a `corkobservatory` directory that contains program source codes, calibration information, etc. To update these files to the latest version you can `cd` into the `corkobservatory` directory and run `svn update` at any time when you have an internet connection.

### 3.1.2 Compile and install mlterm, mlbin, mldat9

`mlterm`, `mlbin` and `mldat9` are the core utilities (programmed in C) to setup CORKs and download the data, strip unnecessary filesystem information from the downloaded `*.raw` files, and to calibrate the data contained in the `*.bin`

files, respectively. In some special cases, when there are problems with data consistency or with special instrument setups you need to use some Python scripts, that will be discussed later, instead of `mldat9`.

Since the core utilities are supplied as C source code, you need to have a C-compiler and basic development tools installed. `cd` into the `mlterm`, `mlbin`, and `mldat` directories under `~/corkobservatory/C-tools` and run

1. `make`
2. `sudo make install`

in each directory to compile and install the programs individually.

NOTE: there is also a variant of `mlterm` `mlterm_vpn` that gets automatically installed with `mlterm` that is for use with instruments connected over connections with high latency (e.g. TCP/IP, VPN,...).

### 3.1.3 Install RS-422 adapter driver if necessary

Many USB/RS-422 adapters run under Linux out of the box, but the *Moxa UPort-1130*, which we found is the most reliable adapter, requires the compilation/installation of a separate driver. We had problems in the past, because the driver was not compatible with current Linux distributions, but fortunately, Moxa did update the driver in summer 2012.

So if you want to use a Moxa adapter make sure to download and install the latest driver either from their [website](#) or use the copy that is stored in the software repository (`~/corkobservatory/ComputerSetup/drivers/MoxaUPort`). Follow the instructions in the `readme.txt` file under “Module driver configuration”.

If the driver install succeeded running `mlterm` with the Moxa UPort plugged into a USB port should start an `mlterm` session with `mlterm` trying to connect to the instrument. If the adapter is not recognized by the OS `mlterm` will fail with the following message:

```
/dev/ttyUSB0: No such file or directory
```

### 3.1.4 Install dependencies for Python scripts

The Python scripts need

1. Python (tested with 2.6 and 2.7)
2. `numpy`
3. `matplotlib` (optionally for plotting)

So first check if Python is already installed `python --version` and install it with e.g. `sudo yum install python` if not. Now you can try to install the `numpy` and `matplotlib` packages of your distribution e.g.:

- `sudo yum install python-numpy`
- `sudo yum install python-matplotlib`

or install `easy_install` e.g. `sudo yum install python-setuptools` and then run:

- `sudo easy_install numpy`
- `sudo easy_install matplotlib`

Now, `cd` into the `~/corkobservatory/ComputerSetup/scripts` directory (see [Check out the CORK software repository](#) for how to set it up) and run `./createPythonToolsSymLinks.bash` to add symbolic links to the python scripts `dumpBin.py` and `calibrateLogfile.py` to your path. If everything worked out, running `dumpBin.py --help` and `calibrateLogfile.py --help` will display the respective help information.

# MANPAGES

Usage: mlterm [OPTION] ... [DEVICE]

Options:

-b BAUDRATE	baudrate for terminal (should match instrument) deflt: 19200
-C	Clear memory
-d FILENAME	debug output file
-D FILENAME	Download data to raw output file
-p FILENAME	parameter error output file (companion to -W)
-F	Full status report
-G FILENAME	Get eeprom and output to parameter file
-h	display this help and exit
-l FILENAME	log output file
-M FILENAME	Metadata (and naked eeprom) to output file
-n HOST[:PORT]	host (and optional network port; default is 4001) for networked serial device
-W FILENAME	Write parameter input file to instrument eeprom
-I	Initial status report
-P	low level (Pass-thru) mlterm for advanced users
-R	Recover communications
-s SITENAME	name as in sites.txt to format data (companion to -U)
-Y	synchronize instrument clock time
-U COUNT	display data in engineering Units for COUNT samples enter '' to display til ESC

-v                    verbose output to screen and log file

DEVICE is the serial port device file; default is /dev/ttyUSB0

Usage: dumpBin.py [options] bin\_files

This script processes ML-CORK bin files

Options:

-h, --help            show this help message and exit

-I RTC\_ID, --RTC\_ID=RTC\_ID

Force RTC ID #. Supply id as hex integer (e.g. 0x8C).

Default: 5th byte in file

-c NCHANNELS, --n\_channels=NCHANNELS

Force number of paro channels

-n, --no\_stats        Skip stats--they can take some time and generate some  
clutter

-s, --spaces

-a, --print\_all

-p, --plot\_data       Plots the data. May not work if you do not have the  
right libraries installed

-i, --info\_only       Just output statistics (and plot, optionally) and not  
the actual data

-o, --old\_ML-CORK     Assume data is from an old ML-CORK where the readings  
do not end with 0x00

-t, --timestamps      Print calibrated timestamps on every line emulating NC  
logfiles, at the same time.

-f TIMESTAMPFMT, --timestampFMT=TIMESTAMPFMT

Modify timestamp format defaults is '%Y%m%d %H:%M:%S'.

Use -f '%Y%m%dT%H%M%S.000Z' to emulate NEPTUNE Canada  
log files.

-d, --despike                Remove detected spikes by inserting linear  
                                 interpolation.  
  
-b BINARYFILE, --binary\_file=BINARYFILE  
                                 Safe a binary file skipping problematic records

Examples:

Usage: calibrateLogfile.py [options] logfile.log

This script find raw data in mlterm logfiles and calibrates it

Options:

-h, --help                show this help message and exit  
  
-c CALIBRATION, --calibration=CALIBRATION  
                                 Name of calibration defined in calibrateData.py  
                                 (required)  
  
-s, --skip\_length\_check  
                                 Skip the check whether the number of calibrated value  
                                 equals the number of                binary input  
                                 fields. Use this e.g. for 1362B where one existing  
                                 channel                contains garbage and is not  
                                 used...



# TODOS

---

## Todo

Add section about NTP setup

---

(The *original entry* is located in C:\Users\Martin\Documents\Instruments\CORKs\corkobservatory\Documentation\src\FieldGuide.rst, line 156.)

---

## Todo

Changed mldat (wrt2dat.c – DEFINE MAXSITES) to support sites.txt files with more than 30 lines. Add same functionality to mldat (formatdata.c) requires CORK simulator for testing...

---

(The *original entry* is located in C:\Users\Martin\Documents\Instruments\CORKs\corkobservatory\Documentation\src\FieldGuide.rst, line 281.)

---





# PYTHON MODULES

Basic functions needed to calibrate ML-CORK / BPR data.

More text to describe what's going on

```
calibrateData.calibratePPCTime (xt=709763880)
```

```
calibrateData.calibrateParoP (xFP, Coeffs=None, xFT=None, Temp=None)
```

```
calibrateData.calibrateParoT (xFT, Coeffs=None)
```

Calibrate temperatures from Paroscientific Type-II gauges.

```
calibrateData.calibratePlatinum (xT, Coeffs=None, ID=None)
```

Calibrate temperatures from platinum chip sensors.

The conversion from A/D counts to temperatures in degC is a simple linear relation ship.

$$T = a \cdot x + b$$

```
calibrateData.calibrateThermistor (xR, Coeffs=None, ID=None)
```

Calibrate temperatures from thermistor.

```
calibrateData.calibrate_1026B (Raw=[11994032, 1736812215, 1753391814])
```

Calibration for the NC 1026B CORK

```
calibrateData.calibrate_1027C (Raw=[5925652, 2199430082L, 2163066709L])
```

Calibration for the setup (SR-2B with new gauges) deployed external to CORK in 1027C in Summer 2011, attached with umbilical

```
calibrateData.calibrate_857D (Raw=[4547430, 2171517024L, 2182222185L])
```

Calibration for the 857D Middle Valley piggyback instrument

```
calibrateData.calibrate_858G (Raw=[4547430, 708836726, 2161941373L, 708836726, 2161941373L])
```

Calibration for the 858G Middle Valley replacement reCORKed in May 2013. Output: T\_Pt, P\_S1, P\_Sf, T\_S1, T\_Sf

```
calibrateData.calibrate_Barkley_BPR78 (Raw=[11627636, 743177769, 2060680196])
```

```
calibrateData.calibrate_DoNet1 (Raw=[6068887, 741081220, 2172977017L, 2172525574L, 2153115213L, 2121447476])
```

Calibration for NanTroSEIZE C02 CORK

```
calibrateData.calibrate_DoNet2_OtherGauges (Raw=[6008878, 741271410, 2172985505L, 2172512813L, 2145168051, 2121430965])
```

```
calibrateData.calibrate_Endavour_BPR83 (Raw=[6471937, 708836726, 2161941373L])
```

```
calibrateData.calibrate_Folger_BPR201107 (Raw=[5128065, 718440432, 2158355974L])
```

```
calibrateData.calibrate_HeissCalib (Raw=[6159243, 692484443, 2131853000])
```

```
calibrateData.calibrate_JFast (Raw=[5965668, 710927413, 2105924590, 720840165,  
2167634962L, 707618831, 2170619802L])
```

Calibration for the 2012 JFast setup

```
calibrateData.calibrate_KEMO_BPR06 (Raw=[5269341, 2160603186L])
```

```
calibrateData.calibrate_NCHR_BPR8C (Raw=[4917899, 2221701693L])
```

```
calibrateData.calibrate_NT_C10_SmartPlug (Raw=[5111502, 710297371, 2165241587L,  
2141217326])
```

```
calibrateData.calibrate_U1362A (Raw=[5908710, 2159359656L, 2233473579L, 2112889090])
```

Calibration for the U1362A (SR2A) setup as it was in stalled on IODP Exp 327 in Jul 2010

```
calibrateData.calibrate_U1362B (Raw=[4740228, 681524504, 2138749542, 2207002754L, 0,  
2135957100])
```

Calibration for the U1362B (initially 1027C) setup as it was in stalled on IODP Exp 327 in Jul 2010. The Screen #3 gauge was just unplugged => crosstalk garbage.

```
calibrateData.calibrate_U1364A (Raw=[5590666, 717083323, 2190506663L, 2166733706L,  
2127403171, 2207142752L, 2128115585])
```

Calibration for IODP U1364A data.

Here are the results of an example calibration:

```
>>> calibrate_U1364A (Raw=[5590666, 717083323, 2190506663, 2166733706, 2127403171, 2207142752, 2128115585]  
[23.626078129440003, 22.276150361949441, 11.103497907947677, 10.510306334848947, 522.67979987438
```

```
calibrateData.getParoCoeffs (ID=None)
```

```
calibrateData.getParoIdList ()
```

```
calibrateData.getPlatinumCoeffs (ID=None)
```

```
calibrateData.getThermistorCoeffs (ID=None)
```

```
calibrateData.readParoCoeffs ()
```

Read coeff from parosci.txt file.

These coeffs are used later on

```
calibrateData.readPlatinumCoeffs ()
```

```
calibrateData.readSites ()
```

Read information from sites.txt file.

```
calibrateData.readThermistorCoeffs ()
```

```
calibrateLogfile.parseCMDOpts ()
```

```
dumpBin.calCoeffs (loggerID)
```

```
dumpBin.getStatistics (Data, loggerID=None, do_plots=False, interp_spikes=False)
```

```
dumpBin.parseCMDOpts ()
```

```
dumpBin.readBinFile (binFileName='1027C_Weekend.bin')
```

```
dumpBin.recordLength (Data, loggerID=None)
```

```
dumpBin.stripTrash (Data)
```

# REFERENCES

*genindex modindex search*



# INDEX

AWQ bulkhead connector, [10](#)

BPR, [10](#)

calCoeffs() (in module dumpBin), [22](#)  
calibrate\_1026B() (in module calibrateData), [21](#)  
calibrate\_1027C() (in module calibrateData), [21](#)  
calibrate\_857D() (in module calibrateData), [21](#)  
calibrate\_858G() (in module calibrateData), [21](#)  
calibrate\_Barkley\_BPR78() (in module calibrateData), [21](#)  
calibrate\_DoNet1() (in module calibrateData), [21](#)  
calibrate\_DoNet2\_OtherGauges() (in module calibrate-Data), [21](#)  
calibrate\_Endeavour\_BPR83() (in module calibrateData), [21](#)  
calibrate\_Folger\_BPR201107() (in module calibrate-Data), [21](#)  
calibrate\_HeissCalib() (in module calibrateData), [21](#)  
calibrate\_JFast() (in module calibrateData), [22](#)  
calibrate\_KEMO\_BPR06() (in module calibrateData), [22](#)  
calibrate\_NCHR\_BPR8C() (in module calibrateData), [22](#)  
calibrate\_NT\_C10\_SmartPlug() (in module calibrate-Data), [22](#)  
calibrate\_U1362A() (in module calibrateData), [22](#)  
calibrate\_U1362B() (in module calibrateData), [22](#)  
calibrate\_U1364A() (in module calibrateData), [22](#)  
calibrateData (module), [21](#)  
calibrateLogfile (module), [22](#)  
calibrateParoP() (in module calibrateData), [21](#)  
calibrateParoT() (in module calibrateData), [21](#)  
calibratePlatinum() (in module calibrateData), [21](#)  
calibratePPCTime() (in module calibrateData), [21](#)  
calibrateThermistor() (in module calibrateData), [21](#)  
CORK, [10](#)

dumpBin (module), [22](#)

getParoCoeffs() (in module calibrateData), [22](#)  
getParoIdList() (in module calibrateData), [22](#)  
getPlatinumCoeffs() (in module calibrateData), [22](#)  
getStatistics() (in module dumpBin), [22](#)  
getThermistorCoeffs() (in module calibrateData), [22](#)

HP-Mini, [11](#)

Moxa UPort, [11](#)

parseCMDOpts() (in module calibrateLogfile), [22](#)  
parseCMDOpts() (in module dumpBin), [22](#)  
readBinFile() (in module dumpBin), [22](#)  
readParoCoeffs() (in module calibrateData), [22](#)  
readPlatinumCoeffs() (in module calibrateData), [22](#)  
readSites() (in module calibrateData), [22](#)  
readThermistorCoeffs() (in module calibrateData), [22](#)  
recordLength() (in module dumpBin), [22](#)  
stripTrash() (in module dumpBin), [22](#)